

Document: #HT000169

Document Title: Setup Database Connection to the LabelView Test Label

Product(s): LabelView

Procedure:

The label needs to be open in LabelView.

Go to Tool – Database Manager.




Click Add.




Check DBF.

Click Next.




Click Browse.




Browse to where you saved the database files.

Click label database.DBF




Click Next.





Click the field for **Connection Name**.

Type in **Test Label Database**.



The database will show up last on the list.





Click File - Exit.

The label is already set up, and is now working.

When you go to print, you can scan in the database information, and LabelView will fill in the missing information.

